


## Manual: Serial Control Manager


by Andreas Bernatzky

*Further Informations : Bachelor Thesis Andreas Bernatzky [1]*

The GUI ArduinoSaveReceive.exe must be in the same folder as the application library kayChart.dll. By double-clicking on the ArduinoSaveReceive.exe, it opens and awaits an assignment of the corresponding COM port to which the Arduino is connected. This must be taken from the Device Manager under Windows (Figure 1). By clicking the “Start” Button the Serial Connection opens. Clicking the “Stop” Button the Connection gets terminates. Make sure you specify the correct Baud-Rate of your device, for example “9600”.




**Figure 1** Arduino Uno assigned to COM4



**Figure 2 GUI with time Intervals**

In section A, a measurement plan can be specified. To do this, select the radio buttons on the Measurement Schedule with "Yes" or "No". It should be noted that due to "Program Properties" all "Measurement Interval 1-3" must contain a value if the Measurement Schedule is used. The time intervals must be specified in seconds. A 5 - 7 - 3 minute measurement interval would look like this (Figure 4)




Measurement Schedule		
Use Measurement Intervals ?	<input checked="" type="radio"/> Yes <input type="radio"/> No	
Measurement Interval 1:	to 300	Set Flow: 60
Measurement Interval 2:	to 720	Set Flow: 80
Measurement Interval 3:	to 910	Set Flow: 100


**Figure 3**

At the beginning of the Measurement Schedule, the timer must be reset via the "Reset Timer" button. Depending on whether you to run in closed-loop-control or open-loop-control, you can select "Open-Loop" or "Closed-Loop" for control under Operation Mode. One of the two operating modes must be selected. If Closed-Loop control is used, the PID-parameters have to be defined in section C. In Open-loop control Setpoint defines an Output Value from 0-255 Bits respectively 0-5V. In Closed-loop control the Setpoint is defined by a value of the temperature or velocity. After the measurement has been carried out, the "Save Data" button must be clicked to save the measurements to your specified Folder for example D:\Packages\Debugger\. The generated .txt file should be renamed to prevent overwriting by a new measurement.

## Closed-loop Control



## Open-loop Control



**Executive Summary:**

1. Connect Arduino computer via USB cable.
2. Run ArduinoSaveReceive.exe.
3. Selection of the COM port via the device manager and set the Baud-Rate.
4. Start the serial communication via the "Start button".
5. Entering setpoint and control parameters.
6. Transfer of setpoint and the control parameters via "Send-Button".
7. (Optional) Specify a directory and Save the measured values via the "Save-Button".
8. Rename the saved file, otherwise risk of overwriting
9. Terminate connection via stop button. Or just unplug the Arduino.

**Acknowledgement:**

*This work has benefitted from funding through the CleanSky2 Programme under Grant Agreement CS2 – LPA – GAM – 2016 -2017 – 01. The authors are responsible for the content of this publication.*

*Company: Fraunhofer IBP*

*Author: Andreas Bernatzky*

*Programm: Serial Control Manager*

*Date: 26.05.2018*

*Description: This GUI was written to visualize Data sent from an Arduino or any other Serial Device.*

## References:

[1] Bernatzky, A.: Aufbau und Regelungstechnischer Entwurf eines Lüfterprüfstandes, Bachelor Thesis at the University of Applied Sciences Rosenheim, 2017, [https://www.fh-rosenheim.de/fileadmin/user\\_upload/Fakultaeten\\_und\\_Abteilungen/Fakultaet\\_ING/Laboratorien/Labor\\_fuer\\_Mess-\\_und\\_Regelungstechnik/Ingenieurprojekte/Aufbau\\_und\\_Regelungstechnischer\\_Entwurf\\_eines\\_Luefter\\_Pruefstandes/Bachelorarbeit\\_A.Bernatzky-Luefterpruefstand.pdf](https://www.fh-rosenheim.de/fileadmin/user_upload/Fakultaeten_und_Abteilungen/Fakultaet_ING/Laboratorien/Labor_fuer_Mess-_und_Regelungstechnik/Ingenieurprojekte/Aufbau_und_Regelungstechnischer_Entwurf_eines_Luefter_Pruefstandes/Bachelorarbeit_A.Bernatzky-Luefterpruefstand.pdf)